

## Startup by Stopping Other Axis

Configurable number of axes		Four axes can be configured independently.
Description	When the axis specified as start-up condition stops, the motor of other axis start automatically.	
Comments	1	<p>When the motor start-up condition is "two or more axes stop";</p> <p>If all the other axes are in stop status when any one axis specified as stop condition starts and stops, the axes to which the condition is configured start.</p> <p>Refer to "<a href="#">Configuration Example 1</a>" for the configuration.</p>
	2	<p>Operating the interpolation motion continuously without changing the interpolation axis;</p> <p>Configure the next motion to <a href="#">pre-register</a>.</p> <p>Refer to "<a href="#">Configuration Example 2</a>" for the configuration.</p>
	3	<p>Operating the interpolation motion continuously by changing the interpolation axis in the middle of the motion</p> <p>Refer to "<a href="#">Configuration Example 3</a>" for the configuration.</p>
Configuration	<p>&lt;<a href="#">Configuration Example 1</a>&gt;</p> <p><b>The motor start-up condition is "two or more axes stop"</b></p> <p>If Y-axis (or X-axis) is in stop status while X-axis (or Y-axis) starts and stops, the motor of U-axis starts.</p> <p>The motor start-up condition for U-axis is "start when the motors of X and Y axes stop". Write the command to start the motor. The motor of U-axis does not start while the start command is written.</p> <p>X-axis : The first axis Y-axis : The second axis U-axis : The forth axis</p>	
	1	<p><b>Multi-function DLL</b></p> <pre> HANDLE hDeviceHandle; int nRet; WORD wSync[4];  hDeviceHandle = MtnOpen("FBIMTN1", MTR_FLAG_NORMAL ); :  wSync[3] = MTR_X   MTR_Y; nRet = MtnSetSync( hDeviceHandle, 0x08, MTR_START_MODE, wSync ); if(nRet != MTR_ERROR_SUCCESS) return -1;  nRet = MtnStartMotion( hDeviceHandle, 0x03, MTR_ACC, MTR_PTP ); nRet = MtnStartMotion( hDeviceHandle, 0x08, MTR_ACC, MTR_JOG ); </pre>

## &lt;Configuration Example 2&gt;

**Operating the interpolation motion continuously without changing interpolation axis using the pre-register**

Perform circular interpolation of X and Y axes, and as continuing the motion, perform linear interpolation 1 motion of X and Y axes.

Use simultaneous start signal as the condition to start the first circular interpolation motion.

1	Set the motor start-up conditions of X and Y axes to "start at the synchronous start signal input".		
2	Configure the circular interpolation motion as follows.		
		X-axis	Y-axis
	Moving direction	CW direction	
	Constant control of combining velocity	OFF	
	Moving velocity	1000 pps	
	Ending coordinate	1000	1000
	Central coordinate	1000	0
	Motion result	90 degree arc	
3	Write command to start the motor.		
4	Configure the linear interpolation 1 motion in the table below for the next motion.		
		X-axis	Y-axis
	Mode	Linear interpolation 1	Linear interpolation 1
	Constant control of combining velocity	OFF	OFF
	Moving step count	1000	5000
	Moving velocity	1000 pps	
	Startup motion	Constant velocity start	Constant velocity start
	Interpolation control axis	O	
	Master/slave axis	Slave axis	Master axis
5	Write command again to start the motor.		
6	The configuration for a series of motor motions is completed. To actually start the motor, output the simultaneous start signal.		

\* When the pre-register is full, the next motion cannot be written.

**2 Multi-function DLL**

```
HANDLE hDeviceHandle;  
int nRet;  
WORD wSync[4];
```

```

MTNARC Arc;
MTNLINE Line;
hDeviceHandle = MtnOpen("FBIMTN1", MTR_FLAG_NORMAL );
:

wSync[0] = MTR_SYNC_EXT;
wSync[1] = MTR_SYNC_EXT;
nRet = MtnSetSync( hDeviceHandle, 0x03, MTR_START_MODE, wSync );

Arc.wAxis = 0x03;
Arc.wClock = 299;
Arc.wMode = MTR_ARC_CW;
Arc.fSpeed = 1000;
Arc.lCenterX = 1000;
Arc.lCenterY = 0;
Arc.lEndX = 1000;
Arc.lEndY = 1000;

nRet = MtnSetMotionArc( hDeviceHandle, MTR_ARC_NORMAL, &Arc );
if(nRet != MTR_ERROR_SUCCESS) return -1;

nRet = MtnStartMotion( hDeviceHandle, 0x03, MTR_CONST, MTR_ARC );
if(nRet != MTR_ERROR_SUCCESS) return -1;

Line.wAxis = 0x03;
Line.wClock = 299;
Line.wMode = MTR_LINE;
Line.wAccMode = MTR_ACC_NORMAL;
Line.fLowSpeed = 100;
Line.fSpeed = 1000;
Line.dwAcc = 100;
Line.dwDec = 100;
Line.fSAccSpeed = 0;
Line.fSDecSpeed = 0;
Line.lStep[0] = 1000;
Line.lStep[1] = 5000;

nRet = MtnSetMotionLine( hDeviceHandle, MTR_LINE_NORMAL, &Line );
if(nRet != MTR_ERROR_SUCCESS) return -1;

nRet = MtnStartMotion( hDeviceHandle, 0x07, MTR_CONST, MTR_LINE );
if(nRet != MTR_ERROR_SUCCESS) return -1;

/* Outputting simultaneous start signal */
nRet = MtnOutputSync(hDeviceHandle, MTR_EXT_START );

```

### <Configuration Example 3>

**Operating interpolation motion of X, Y, Z axes continuously as follows**

	X	Y	Z	Description
--	---	---	---	-------------

1	Center point	1000	0		X and Y axes: radius 1000, 90 degree circular interpolation motion
	End point	1000	1000	0	X axis: moving pulse count 0, PTP motion
	Startup condition	Synchronous start	Synchronous start	Waiting for X and Y-axes stop	
2	Moving pulse count	1000		-5000	X and Z axes: linear interpolation 1
	Startup condition	Waiting for Z-axis stop		Continuous startup (No conditions)	

Use simultaneous start signal as the condition to start the first [circular interpolation motion](#).

1	Configure as follows; Y and Z-axes motor start-up condition: "start at the synchronous start signal input", Z-axis motor start-up condition: "start when X and Y axes stop".
2	Configure circular interpolation for X and Y-axes. Configure PTP motion of moving pulse count 0 for Z axis.
3	Write command to start the motor.
4	Configure as follows; X-axis motor start-up condition: "start when Z axis stops", Y and Z-axes motor start-up condition: "No start condition".
5	Configure linear interpolation 1 motion for X and Z axes.
6	Write command again to start the motor.
7	The configuration for a series of motor motions is completed. To actually start the motor, output the simultaneous start signal.

\* When the [pre-register](#) is full, the next motion cannot be written.

3	<b>Multi-function DLL</b>
	<pre> HANDLE hDeviceHandle; int nRet; WORD wSync[4]; MTNARC Arc; MTNLINE Line; MTNMOTION Motion[3]; hDeviceHandle = MtnOpen("FBIMTN1", MTR_FLAG_NORMAL ); : </pre>

```
// ===== step 1 =====

wSync[0] = MTR_SYNC_EXT;
wSync[1] = MTR_SYNC_EXT;
wSync[2] = MTR_X | MTR_Y;
nRet = MtnSetSync( hDeviceHandle, 0x07, MTR_START_MODE, wSync );

Arc.wAxis = 0x03;
Arc.wClock = 299;
Arc.wMode = MTR_ARC_CW;
Arc.fSpeed = 1000;
Arc.lCenterX = 1000;
Arc.lCenterY = 0;
Arc.lEndX = 1000;
Arc.lEndY = 1000;

nRet = MtnSetMotionArc( hDeviceHandle, MTR_ARC_NORMAL, &Arc );
if(nRet != MTR_ERROR_SUCCESS) return -1;

nRet = MtnStartMotion( hDeviceHandle, 0x03, MTR_CONST, MTR_ARC );
if(nRet != MTR_ERROR_SUCCESS) return -1;

Motion[2].wClock = 299;
//Motion[2].wMode = MTR_PTP;
Motion[2].wAccMode = MTR_ACC_NORMAL;
Motion[2].fLowSpeed = 10;
Motion[2].fSpeed = 500;
Motion[2].dwAcc = 100;
Motion[2].dwDec = 100;
Motion[2].fSAccSpeed = 0;
Motion[2].fSDecSpeed = 0;
Motion[2].lStep = 0;

nRet = MtnSetMotion( hDeviceHandle, 0x04, MTR_PTP, Motion );

nRet = MtnStartMotion( hDeviceHandle, 0x04, MTR_CONST, MTR_PTP );

// ===== step 2 =====

wSync[0] = MTR_Z;
wSync[1] = MTR_NO;
wSync[2] = MTR_NO;
nRet = MtnSetSync(hDeviceHandle, 0x07, MTR_START_MODE, wSync);

Line.wAxis = 0x05;
Line.wClock = 299;
Line.wMode = MTR_LINE;
Line.wAccMode = MTR_ACC_NORMAL;
Line.fLowSpeed = 100;
Line.fSpeed = 700;
```

```
Line.dwAcc = 100;
Line.dwDec = 100;
Line.fSAccSpeed = 0;
Line.fSDecSpeed = 0;
Line.lStep[0] = 1000;
Line.lStep[2] = -5000;

nRet = MtnSetMotionLine( hDeviceHandle, MTR_LINE_NORMAL, &Line );
if(nRet != MTR_ERROR_SUCCESS) return -1;

/* Synchronous start signal output */
nRet = MtnOutputSync(hDeviceHandle, MTR_EXT_START );
```

© 2003, 2015 Interface Corporation. All rights reserved.

[\[Top\]](#)